# Package 'gasfluxes'

July 22, 2025
Type Package
Title Greenhouse Gas Flux Calculation from Chamber Measurements
Version 0.7
<b>Date</b> 2024-08-16
<b>Description</b> Functions for greenhouse gas flux calculation from chamber measurements.
<pre>URL https://git-dmz.thuenen.de/fuss/gasfluxes</pre>
License GPL (>= 2)
<b>Depends</b> R (>= $4.3.0$ )
<b>Imports</b> sfsmisc, data.table (>= 1.14.8), MASS, stats, graphics, grDevices
Suggests testthat, knitr, rmarkdown
LazyData true
Encoding UTF-8
VignetteBuilder knitr, rmarkdown
RoxygenNote 7.3.2
NeedsCompilation no
Author Roland Fuss [aut, cre] (ORCID: <a href="https://orcid.org/0000-0002-0274-0809">https://orcid.org/0000-0001-0002-0274-0809</a> ), Roman Hueppi [ctb] (ORCID: <a href="https://orcid.org/0000-0001-8815-7835">https://orcid.org/0000-0001-8815-7835</a> )
Maintainer Roland Fuss < roland.fuss@thuenen.de>
Repository CRAN
<b>Date/Publication</b> 2024-08-16 08:50:02 UTC
Contents
agg.fluxes

2 agg.fluxes

HMR.fit																 					(	ó
lin.fit																 					9	)
$\ensuremath{NDFE}.\ensuremath{fit}$																 					10	)
rlin.fit																 					12	2
selectfluxes																 					13	3

Index 16

## Description

Aggregate a time series of fluxes to a cummulative flux value.

#### Usage

```
agg.fluxes(fluxes, datetimes, timeunit = "hours")
```

## **Arguments**

fluxes flux values

datetimes datetime values (POSIXct or POSIXlt)

timeunit the unit of time (denominator of the flux unit), supported are the explicit units

supported by difftime

## **Details**

The function uses linear interpolation. The unit of the cumulative flux is [fluxes] \* timeunit. NA values are removed and values sorted according to time order. If less then two non-NA value pairs are provided, NA is returned for the cumulative flux.

#### Value

A one-row data.frame with columns

flux the cumulative flux

from the start of the cumulation period to the end of the cumulation period

The return value being a data.frame is useful, when the function is used for "split-apply-combine" type operations to calculate groupwise cumulated values, e.g., using package data.table.

erfc 3

#### **Examples**

```
#Some random example data
datetimes <- Sys.time() + (1:20)/2*24*3600
set.seed(42)
fluxes <- rlnorm(20, 5)
agg.fluxes(fluxes, datetimes)</pre>
```

erfc

erfc

## Description

This is the complementary error function.

## Usage

erfc(x)

## Arguments

Х

a numeric vector

#### Value

A numeric vector, i.e., the erfc values.

fluxMeas

Data from chamber N2O flux measurements.

## Description

A dataset containing data from 1329 chamber N2O flux measurements.

#### **Format**

A data.table with 5300 rows and 5 variables:

- serie: ID of flux measurement
- V: Volume (normalized by area, i.e., the height in m)
- A: Area (always 1)
- time: closing time in h
- C: N2O concentration in mg N / m^3

#### **Source**

own data (anonymized by not including site and treatment information)

4 gasfluxes

gasfluxes

Flux calculation

## Description

A wrapper function for convenient flux calculation.

## Usage

```
gasfluxes(
    dat,
    .id = "ID",
    .V = "V",
    .A = "A",
    .times = "time",
    .C = "C",
    methods = c("linear", "robust linear", "HMR", "NDFE"),
    k_HMR = log(1.5),
    k_NDFE = log(0.01),
    verbose = TRUE,
    plot = TRUE,
    select,
    maxiter = 100,
    ...
)
```

## Arguments

dat	a data.frame or data.table with data from flux measurements.
.id	character vector specifying the columns to be used as ID, multiple ID columns are possible.
. V	character specifying the column containing chamber volume values.
. A	character specifying the column containing chamber area values.
.times	character specifying the column containing chamber closing time values.
. C	character specifying the column containing concentration values.
methods	character; which methods to use for flux estimation. See details for available methods.
k_HMR	starting value for HMR.fit.
k_NDFE	starting value for NDFE.fit.
verbose	logical; print progress messages?
plot	create a PDF with plots in the working directory if TRUE (the default). The IDs are used as plot names. The plots are only intended to facilitate quick checking, not for publication quality graphs.
select	deprecated; please use function selectfluxes.

gasfluxes 5

```
maxiter see nls.control
... further parameters
```

#### **Details**

Available methods are

```
"linear": lin.fit
"robust linear": rlin.fit
"HMR": HMR.fit
"NDFE": NDFE.fit
```

Specifying other methods results in an error.

The default starting values for "HMR" and "NDFE",  $k = log(\kappa)$  and  $k = log(\tau)$ , resp., assume that time is in hours. If you use a different time unit, you should adjust them accordingly. Note that nls is used internally by these functions and thus they should not be used with artificial "zero-residual" data.

The input data.frame or data.table should be in the following format:

```
        serie
        V A
        time
        C

        1:
        ID1 0.522625 1 0.0000000 0.3317823

        2:
        ID1 0.522625 1 0.3333333 0.3304053

        3:
        ID1 0.522625 1 0.6666667 0.3394311

        4:
        ID1 0.522625 1 1.0000000 0.4469102

        5:
        ID2 0.523625 1 0.0000000 0.4572708
```

However, more than one ID column are possible. E.g., the first ID column could be the plot and a second ID column could be the date. Keep in mind that the combination of IDs must be a unique identifier for each flux measurement.

Units of the output depend on input units. It's recommended to use  $[V] = m^3$ ,  $[A] = m^2$ , [time] = h,  $[C] = [mass or mol]/m^3$ , which results in  $[f0] = [mass or mol]/m^2/h$ . Since all algorithms use V/A, A can be input as 1 and V as the chamber height.

#### Value

A data table with the results of the flux calculation. See the documentation of the fitting functions for details. If a selection algorithm has been specified, the last columns are the selected flux estimate, the corresponding standard error and p-value and the method with which the selected flux was estimated.

#### See Also

selectfluxes for flux selection

6 HMR.fit

#### **Examples**

```
## Not run:
#compare result of original HMR with plinear HMR
data(fluxMeas)
res <- gasfluxes(fluxMeas[1:400,],</pre>
                 .id = "serie", .V = "V", .A = "A",
                 .times = "time", .C = "C",
                 methods = c("HMR"), verbose = TRUE)
#number of successful fits
res[, sum(!is.na(HMR.kappa))]
res <- gasfluxes(fluxMeas,</pre>
                 .id = "serie", .V = "V", .A = "A",
                 .times = "time", .C = "C",
                 methods = "HMR", verbose = TRUE)
# Error: time not sorted in flux ID ID556.
# Investigate the problem:
fluxMeas[serie %in% c("ID555", "ID556", "ID557")]
    serie
            V A time
                                   С
# 1: ID555 0.551625 1 0.0000000 0.3884388
# 2: ID555 0.551625 1 0.3333333 0.4125270
# 3: ID555 0.551625 1 0.6666667 0.3714207
# 4: ID555 0.551625 1 1.0000000 0.3735092
# 5: ID556 0.524250 1 0.0000000 0.3638239
# 6: ID556 0.524250 1 0.3333333 0.3520481
# 7: ID556 0.524250 1 0.6666667 0.3551644
# 8: ID557 0.528375 1 0.0500000 0.3954601
# 9: ID556 0.524250 1 0.0000000 0.3839834
#10: ID557 0.528375 1 0.3333333 0.3967269
#11: ID557 0.528375 1 0.6666667 0.3764967
#12: ID557 0.528375 1 1.0000000 0.3973055
# some mixup of IDs and times
# usually an input or Excel error during data preparation
# investigate and fix
## End(Not run)
```

HMR.fit

HMR fit

#### Description

Fit the HMR model using the Golub-Pereyra algorithm for partially linear least-squares models.

HMR.fit 7

#### Usage

```
HMR.fit(
    t,
    C,
    A = 1,
    V,
    serie = "",
    k = log(1.5),
    verbose = TRUE,
    plot = FALSE,
    maxiter = 100,
    ...
)
```

#### **Arguments**

t	time values (usually in hours)
С	concentration values
A	area covered by the chamber
V	effective volume of the chamber
serie	id of the flux measurement
k	starting value for nls function
verbose	logical, TRUE prints message after each flux calculation
plot	logical, mainly intended for use in gasfluxes
maxiter	see nls.control
	further parameters, currently none

## Details

The HMR model (Pedersen et al., 2010) is  $C(t) = \phi + f_0 \frac{e^{-\kappa t}}{-\kappa \frac{V}{A}}$ . To ensure the lower bound  $\kappa > 0$ , the substitution  $\kappa = e^k$  is used. The resulting reparameterized model is then fit using nls with algorithm = "plinear". This is computationally more efficient than the manual implementation in the HMR package and results in almost identical flux values. Flux standard errors and p-values differ strongly from those reported by the HMR package <= version 0.3.1, but are equal to those reported by later versions.

The default starting value  $k = log(\kappa)$  assumes that time is in hours. If you use a different time unit, you should adjust it accordingly.

There have been demands to return the initial concentration as predicted by the model as this is useful for checking plausibility. However, this can be easily calculated from the parameters and the equation of the model by setting t=0, i.e.,  $C_0=\phi-\frac{f_0}{\kappa\frac{V}{A}}$ .

Note that nls is used internally and thus this function should not be used with artificial "zero-residual" data.

8 HMR.fit

#### Value

A list of f0 flux estimate standard error of flux estimate f0.se f0.p p-value of flux estimate other parameters of the HMR model kappa, phi AIC Akaike information criterion AICc Akaike information criterion with small sample correction RSF residual standard error (sigma from summary.nls) error or warning messages diagnostics

#### References

Pedersen, A.R., Petersen, S.O., Schelde, K., 2010. A comprehensive approach to soil-atmosphere trace-gas flux estimation with static chambers. European Journal of Soil Science 61(6), 888-902.

## **Examples**

```
#a single fit
t < -c(0, 1/3, 2/3, 1)
C <- c(320, 341, 352, 359)
print(fit <- HMR.fit(t, C, 1, 0.3, "a"))</pre>
plot(C \sim t)
curve({fit$phi + fit$f0 * exp(-fit$kappa * x)/(-fit$kappa*0.3)},
      from = 0, to = 1, add = TRUE)
## Not run:
#a dataset of 1329 chamber N2O flux measurements
data(fluxMeas)
fluxMeas[, n := length(time), by=serie]
print(fluxMeas)
fluxes <- fluxMeas[n > 3, HMR.fit(time, C, A, V, serie), by=serie]
print(fluxes)
plot(f0.se ~ f0, data = fluxes)
#one very large f0.se value (and several infinite ones not shown in the plot)
fluxes[is.finite(f0.se),][which.max(f0.se),]
plot(C~time, data=fluxMeas[serie=="ID940",])
print(tmp <- fluxes[is.finite(f0.se),][which.max(f0.se),])</pre>
curve(\{tmp[, phi] + tmp[, f0] * exp(-tmp[, kappa] * x)/
      (-tmp[, kappa]*fluxMeas[serie=="ID940", V[1]]/
      fluxMeas[serie=="ID940",A[1]])},
      from = 0, to = 1, add = TRUE)
plot(f0.se \sim f0, data = fluxes[f0.se < 1e4,], pch = 16)
boxplot(fluxes[f0.se < 1e4, sqrt(f0.se)])</pre>
## End(Not run)
```

lin.fit 9

lin.fit	Linear concentration - time model	
---------	-----------------------------------	--

## Description

Fit a linear model to concentration - time data.

## Usage

```
lin.fit(t, C, A = 1, V, serie = "", verbose = TRUE, plot = FALSE, ...)
```

## Arguments

`	•	
	t	time values (usually in hours)
	С	concentration values
	A	area covered by the chamber
	V	effective volume of the chamber
	serie	id of the flux measurement
	verbose	logical, TRUE prints message after each flux calculation
	plot	logical, mainly intended for use in gasfluxes
		further parameters, currently none

## **Details**

This is basically a wrapper of R's OLS fitting facilities. For now 1m (and methods for objects of class "lm") is used, but this may change to more efficient alternatives in later versions.

## Value

A list of	
f0	flux estimate
f0.se	standard error of flux estimate
f0.p	p-value of flux estimate
C0	estimated concentration at $t = 0$ (intercept)
AIC	Akaike information criterion
AICc	Akaike information criterion with small sample correction
RSE	residual standard error (sigma from summary.nls)
r	Pearson's correlation coefficient
diagnostics	error or warning messages

NDFE.fit

## **Examples**

```
#a single fit
t <- c(0, 1/3, 2/3, 1)
C <- c(320, 341, 352, 359)
print(fit <- lin.fit(t, C, 1, 0.3, "a"))
plot(C ~ t)
curve({fit$f0/0.3 * x + fit$C0}, from = 0, to = 1, add = TRUE)</pre>
```

NDFE.fit

NDFE fit

## **Description**

Fit the non-steady-state diffusive flux extimator model using the Golub-Pereyra algorithm for partially linear least-squares models.

## Usage

```
NDFE.fit(
    t,
    C,
    A = 1,
    V,
    serie = "",
    k = log(0.01),
    verbose = TRUE,
    plot = FALSE,
    maxiter = 100,
    ...
)
```

#### **Arguments**

```
t
                  time values (usually in hours)
С
                  concentration values
                  area covered by the chamber
Α
                  effective volume of the chamber
                  id of the flux measurement
serie
                  starting value for nls function
                  logical, TRUE prints message after each flux calculation
verbose
plot
                  logical, mainly intended for use in gasfluxes
maxiter
                  see nls.control
                  further parameters, currently none
```

NDFE.fit

#### **Details**

The NDFE model (Livingston et al., 2006) is  $C(t) = C_0 + f_0 \tau \frac{A}{V} \left[ \frac{2}{\sqrt{\mathrm{pi}}} \sqrt{t/\tau} + e^{t/\tau} \mathrm{erfc}(\sqrt{t/\tau}) - 1 \right]$ .

To ensure the lower bound  $\tau > 0$ , the substituion  $\tau = e^k$  is used. The resulting reparameterized model is then fit using nls with algorithm = "plinear".

Note that according to the reference the model is not valid for negative fluxes. Warning: This function does not check if fluxes are positive. It's left to the user to handle negative fluxes.

The default starting value  $k = log(\tau)$  assumes that time is in hours. If you use a different time unit, you should adjust it accordingly.

Note that nls is used internally and thus this function should not be used with artificial "zero-residual" data.

#### Value

A list of	
f0	flux estimate
f0.se	standard error of flux estimate
f0.p	p-value of flux estimate
C0, tau	other parameters of the NDFE model
AIC	Akaike information criterion
AICc	Akaike information criterion with small sample correction
RSE	residual standard error (sigma from summary.nls)
diagnostics	error or warning messages

## References

Livingston, G.P., Hutchinson, G.L., Spartalian, K., 2006. Trace gas emission in chambers: A non-steady-state diffusion model. Soil Sci. Soc. Am. J. 70(5), 1459-1469.

## Examples

12 rlin.fit

rlin.fit Robust linear conc	entration - time model
-----------------------------	------------------------

## Description

Fit a linear model to concentration - time data using robust methods.

## Usage

```
rlin.fit(t, C, A = 1, V, serie = "", verbose = TRUE, plot = FALSE, ...)
```

## Arguments

t	time values (usually in hours)
С	concentration values
A	area covered by the chamber
٧	effective volume of the chamber
serie	id of the flux measurement
verbose	logical, TRUE prints message after each flux calculation
plot	logical, mainly intended for use in gasfluxes
	further parameters, currently none

## **Details**

This is basically a wrapper of rlm using the Huber M estimator. This function never weights the first or last time point with zero with very few data points. However, there might exist "better" robust regression methods for flux estimation.

## Value

A list of	
f0	flux estimate
f0.se	standard error of flux estimate
f0.p	p-value of flux estimate
C0	estimated concentration at $t = 0$ (intercept)
weights	robustness weights
diagnostics	error or warning messages

selectfluxes 13

#### **Examples**

```
#a single fit
t <- c(0, 1/3, 2/3, 1)
C <- c(320, 330, 315, 351)
print(fit <- rlin.fit(t, C, 1, 0.3, "a"))
plot(C ~ t)
curve({fit$f0/0.3 * x + fit$C0}, from = 0, to = 1, add = TRUE)</pre>
```

selectfluxes

Select a flux estimate

## **Description**

Selects the appropriate flux estimate from linear, robust linear and non-linear calculated fluxes.

#### Usage

```
selectfluxes(dat, select, f.detect = NULL, t.meas = NULL, tol = 5e-05, ...)
```

## Arguments

dat select	a data.table as returned by gasfluxes. The function modifies it by reference. character; specify a ruleset for selection of the final flux value, see details.
f.detect	detection limit for HMR method. This can be determined by a simple simulation (see examples) or for four data points the approximation in Parkin et al. (2012) can be used.
t.meas	a vector or single value giving the measurement time factor that relates to kappa.max. It is suggested to use the time difference between the first and last sample taken from the closed chamber. The unit should be consistent with the units of f.detect and kappa (e.g., h if kappa is in 1/h).
tol	the relative tolerance abs((linear.f0 - HMR.f0)/HMR.f0) below which the linear flux estimate and the HMR flux estimate are considered equal in the "kappa.max" algorithm. This is to protect against HMR fits that equal the linear fit and have extremely high standard errors. Defaults to tol = 5e-5.
	further parameters

#### **Details**

Available selection algorithms currently are

"kappa.max" The selection algorithm restricts the use of HMR by imposing a maximal value for kappa "kappa.max", depending on the quotient of the linear flux estimate and the minimal detectable flux (f.detect), as well as the chamber closure time (t.meas). kappa.max = f.lin/f.detect/t.meas. This is currently the recommended algorithm. Note that the algorithm was developed for predominantly positive fluxes (such as N2O fluxes). If data with considerable gas uptake is analyzed, the algorithm needs to be modified, which currently means the user needs to implement it themselves.

14 selectfluxes

Other selection algorithms could be implemented, but selection can always be done as a postprocessing step. E.g., if many data points are available for each flux measurement it is probably most sensible to use AICc.

#### Value

A data.table with the with following columns added to the function input: selected flux estimate, the corresponding standard error and p-value and the method with which the selected flux was estimated. For the "kappa.max" method the "kappa.max" values are included. These columns are also added to the input data.table by reference.

#### References

Parkin, T.B., Venterea, R.T., Hargreaves, S.K., 2012. Calculating the Detection Limits of Chamberbased Soil Greenhouse Gas Flux Measurements. Journal of Environmental Quality 41, 705-715.

Hueppi, R., Felber, R., Krauss, M., Six, J., Leifeld, J., Fuss, R., 2018. Restricting the nonlinearity parameter in soil greenhouse gas flux calculation for more reliable flux estimates. PLOS ONE 13(7): e0200876. https://doi.org/10.1371/journal.pone.0200876

#### **Examples**

```
## Not run:
res <- gasfluxes(fluxMeas[1:499],</pre>
                 .id = "serie", .V = "V", .A = "A",
                 .times = "time", .C = "C",
             methods = c("linear", "robust linear", "HMR"), verbose = FALSE, plot = FALSE)
### estimate f.detect by simulation ###
#ambient concentration:
C0 <- 320/1000 * 28 * 273.15 / 22.4 / (273.15 + 15) #mg N / m^3
#uncertainty of GC measurement:
sdGC <- 5/1000 * 28 * 273.15 / 22.4 / (273.15 + 15) #mg N / m^3
#create simulated concentrations corresponding to 1 hour flux measurements with zero fluxes:
set.seed(42)
sim < -data.frame(t = seq(0, 1, length.out = 4), C = rnorm(4e3, mean = C0, sd = sdGC),
                  id = rep(1:1e3, each = 4), A = 1, V = 0.52)
#fit HMR model:
simflux <- gasfluxes(sim, .id = "id", .times = "t", methods = c("HMR", "linear"), plot = FALSE)
simflux[, f0 := HMR.f0]
simflux[is.na(f0), f0 := linear.f0]
#dection limit as 97.5 % quantile (95 % confidence):
f.detect <- simflux[, quantile(f0, 0.975)] #0.03 mg N / m^2 / h
# example using the kappa.max (ref. Hueppi et al., 2018) with a single t.meas value
t.meas <- max(fluxMeas$time[1:499]) #1</pre>
selectfluxes(res, "kappa.max", f.detect = f.detect, t.meas = t.meas)
res[method == "HMR", .N] # 11
# example using the kappa.max with a vector for t.meas
t.meas \leftarrow fluxMeas[1:499][, max(time), by = serie][["V1"]]
selectfluxes(res, "kappa.max", f.detect = f.detect, t.meas = t.meas)
```

selectfluxes 15

```
res[method == "HMR", .N] # 10
## End(Not run)
```

## **Index**

```
agg.fluxes, 2
erfc, 3
fluxMeas, 3
gasfluxes, 4, 7, 9, 10, 12, 13
HMR.fit, 4, 5, 6
lin.fit, 5, 9
lm, 9
NDFE.fit, 4, 5, 10
nls, 7, 11
nls.control, 5, 7, 10
rlin.fit, 5, 12
rlm, 12
selectfluxes, 4, 5, 13
```